

ADD/REMOVE METADATA SERVER

With `ceph-deploy`, adding and removing metadata servers is a simple task. You just add or remove one or more metadata servers on the command line with one command.

Important: You must deploy at least one metadata server to use CephFS. There is experimental support for running multiple metadata servers. Do not run multiple active metadata servers in production.

See [MDS Config Reference](#) for details on configuring metadata servers.

ADD A METADATA SERVER

Once you deploy monitors and OSDs you may deploy the metadata server(s).

```
ceph-deploy mds create {host-name}[:{daemon-name}] [{host-name}[:{daemon-name}] ...]
```

You may specify a daemon instance a name (optional) if you would like to run multiple daemons on a single server.

REMOVE A METADATA SERVER

Coming soon...